



Flux of a vector field through a surface

$\vec{u}(x, y, z)$ = field of velocity of some fluid.



Flux of \vec{u} through S tells how much fluid passes through S .

(orientable)




Surface has "positive side" and "negative side".

To get from one to the other, we need to cross an edge


How much fluid flows through surface, from $\ominus \rightarrow \oplus$ side?

Flux is positive if fluid crosses from $\ominus \rightarrow \oplus$. Neg otherwise \ominus




Here the total amount of fluid passing through surface may be zero, since equal amounts cross from $\ominus \rightarrow \oplus$ and $\oplus \rightarrow \ominus$.

Sometimes the flux is not zero!




unit normal vector
field $\hat{n}(x, y, z)$.

If flow goes in direction of normal,
then the flux is maximal.



If, on the other hand, \vec{u} is tangent
then it gives no contribution.



Formula for Flux:

$$\Phi = \iint_S \vec{u} \cdot \vec{n} \, dS$$

↑
Greek letter "Phi"

Suppose: $\vec{u} = (P(x, y, z), Q(x, y, z), R(x, y, z))$

Surface: $S: z = f(x, y) \quad (x, y) \in D \subset \mathbb{R}^2$
or
 $\varphi(x, y, z) = 0$ with $\varphi(x, y, z) := z - f(x, y)$

Normal vector:

Normal vector is in direction of gradient $\nabla \varphi$,



since φ does not change when moving along S , infinitesimally, thus

$$\vec{T} \cdot \nabla \varphi = 0$$

for all tangential directions \vec{T} .

We compute: $\vec{n} = \frac{\nabla\phi}{|\nabla\phi|}$ where

$$\phi = z - f(x, y)$$

$$\nabla\phi = (-f_x, -f_y, 1)$$

$$|\nabla\phi| = \sqrt{f_x^2 + f_y^2 + 1}$$

Thus

$$\vec{n}(x, y, f(x, y)) = \frac{(-f_x, -f_y, 1)}{\sqrt{f_x^2 + f_y^2 + 1}}$$

This vector looks "up", as third component is positive. surface with upperside positive



\vec{n} points from \ominus to \oplus side.

$$\phi = \iint_S \vec{u} \cdot \vec{n} \, dS$$

$$= \iint_S (P, Q, R) \cdot \left(\frac{-f_x}{\sqrt{f_x^2 + f_y^2 + 1}}, \frac{-f_y}{\sqrt{f_x^2 + f_y^2 + 1}}, \frac{1}{\sqrt{f_x^2 + f_y^2 + 1}} \right) dS$$

$$= \iint_D (P, Q, R) \cdot (-f_x, -f_y, 1) \, dA$$

$dS = \sqrt{f_x^2 + f_y^2 + 1} \, dA$

$$= \iint_D \left(P(x, y, f(x, y)) (-f_x) + Q(x, y, f(x, y)) (-f_y) + R(x, y, f(x, y)) \right) dA$$

Luckily, nasty square roots disappear!

$$\phi = \iint_D (-Pf_x - Qf_y + R) dA$$



Example $\vec{u}(x, y, z) = (x, y, -2z)$

$$S: z = a(1 - x^2 - y^2) \quad a \in \mathbb{R}.$$

$$D: x^2 + y^2 \leq 1$$

Surface is a piece of paraboloid:

$$P = x, \quad Q = y, \quad R = -2z$$



$$f = a(1 - x^2 - y^2) \quad f_x = -2ax \quad f_y = -2ay$$

$$\phi = \iint_D (2ax^2 + 2ay^2 - 2a(1 - x^2 - y^2)) dA$$


$$= \iint_D (4a(x^2 + y^2) - 2a) dA$$

$$\phi = \iint_D (4a(x^2+y^2) - 2a) dA$$

$$= \int_0^{2\pi} \int_0^1 (4ar^2 - 2a) r dr d\theta$$

$$= 2\pi \int_0^1 (4ar^3 - 2ar) dr$$

$$= 2\pi \left(4a \cdot \frac{1}{4} - 2a \cdot \frac{1}{2} \right) = 0 !$$



Look! we had a parameter "a".

If $a=0$, our surface was the disk D .

But \vec{u} is tangent to D , so there is no flux.

For positive "a", the flux is still zero since fluid enters/exits in the same proportion. This will be a special case of a very general result...